



ATMS Installation Guide

If you are upgrading from an existing application and database please ensure that you have a current backup before proceeding

Evaluation Install

The evaluation setup installs a blank database and 30 day licence file to the following directory: [Install Path]\Database\

1. Close all Windows programs and log on as a user with full administrative privileges
2. Place the ATMS CD into the CD/DVD Drive or download the setup file from the ISIS website
3. Browse to the setup.exe file on the CD or the downloaded setup file and double click to open
4. Follow the on-screen Instructions to complete the Database Installation

The default login details for ATMS are

Username: ADMIN
Password: ADMIN

In order to Unlock the software to a full version of ATMS, or to extend the evaluation period once it has expired, please contact your software supplier for an Unlock code

New Installation

Installation of ATMS

1. Close all Windows programs and log on as a user with full administrative privileges
2. Place the ATMS CD into the CD/DVD Drive or download the setup file from the ISIS website
3. Browse to the setup.exe file on the CD or to the downloaded installation file and double click to open
4. Follow the on-screen Instructions to complete the ATMS Installation

During the installation process you will be required to specify the following:

- The destination folder where you wish to install ATMS
 - Whether to backup files replaced during the installation and if so where you would like these files saved
 - The name of the Program Manager group you wish to add the ATMS icons to
5. Select ATMS Config from the program Manager Group where you placed the ATMS icons. From this configuration screen select the database path for the ATMS Database and the language you wish to use. Once the selections have been made Save and Exit
 6. Select ATMS from the Program Manager group where you installed ATMS in order to run the program. This will run a demo version of ATMS

The default login details for ATMS are

Username: ADMIN
Password: ADMIN

In order to Unlock the software to a full version of ATMS, or to extend the evaluation period once it has expired, please contact your software supplier for an Unlock code

Installation of a blank ATMS Database

1. Close all Windows programs
2. Place the ATMS CD into the CD/DVD Drive or download the setup file from the ISIS website
3. Browse to the SetupDB.exe file on the CD or to the downloaded installation file and double click to open
4. Follow the on-screen Instructions to complete the ATMS Installation

Upgrading ATMS

ATMS Upgrade from version 1.3 or higher

1. Close all Windows programs
2. Place the ATMS CD into the CD/DVD Drive or download the setup file from the ISIS website
3. Browse to the update.exe file on the CD or to the downloaded installation file and double click to open
4. Follow the on-screen Instructions to complete the ATMS Installation

ATMS Upgrade from version 1.2

Follow the instructions as above then:

5. Copy the amts.lic file from the Licence folder on the CD and place it in the same folder as the ATMS Database
6. Contact your software supplier to obtain an unlock code

When you first run ATMS following an upgrade you may be prompted to update the database; follow the on screen instructions to complete the update process

System Requirements

Supported platforms

- Windows 98 SE
- Windows ME
- Windows 2000 Professional
- Windows NT 4.0 SP6
- Windows XP Professional
- Windows Vista*

*user account control (UAC) must be disabled to allow ATMS to run correctly

Hardware - Recommended Spec

- Pentium 3 Processor or equivalent
- 1024 x 768 screen resolution
- 128 MB RAM

Hardware - Minimum Spec

- Pentium 2 Processor or equivalent
- 800 x 600 screen resolution
- 64 MB RAM

For SQL Server Databases

- SQL Server 2000
- SQL Server Express